



United States Department of Agriculture  
Food Safety and Inspection Service

## Food Safety Information



# Keeping Food Safe During an Emergency

*Did you know that a flood, fire, national disaster, or the loss of power from high winds, snow, or ice could jeopardize the safety of your food? Knowing how to determine if food is safe and how to keep food safe will help minimize the potential loss of food and reduce the risk of foodborne illness. This fact sheet will help you make the right decisions for keeping your family safe during an emergency.*

### ABCD's of Keeping Food Safe in an Emergency

Always keep meat, poultry, fish, and eggs refrigerated at or below 40 °F and frozen food at or below 0 °F. This may be difficult when the power is out.

Keep the refrigerator and freezer doors closed as much as possible to maintain the cold temperature. The refrigerator will keep food safely cold for about 4 hours if it is unopened. A full freezer will hold the temperature for approximately 48 hours (24 hours if it is half full) if the door remains closed. Obtain dry or block ice to keep your refrigerator as cold as possible if the power is going to be out for a prolonged period of time. Fifty pounds of dry ice should hold an 18-cubic foot full freezer for 2 days. Plan ahead and know where dry ice and block ice can be purchased.

### Be prepared for an emergency...

...by having items on hand that don't require refrigeration and can be eaten cold or heated on the outdoor grill. Shelf-stable food, boxed or canned milk, water, and canned goods should be part of a planned emergency food supply. Make sure you have ready-to-use baby formula for infants and pet food. Remember to use these items and replace them from time to time. Be sure to keep a hand-held can opener for an emergency.

Consider what you can do ahead of time to store your food safely in an emergency. If you live in a location that could be affected by a flood, plan your food storage on shelves that will be safely out of the way of contaminated water. Coolers are a great help

for keeping food cold if the power will be out for more than 4 hours-have a couple on hand along with frozen gel packs. When your freezer is not full, keep items close together-this helps the food stay cold longer.

Digital, dial, or instant-read food thermometers and appliance thermometers will help you know if the food is at safe temperatures. Keep appliance thermometers in the refrigerator and freezer at all times. When the power is out, an appliance thermometer will always indicate the temperature in the refrigerator and freezer no matter how long the power has been out. The refrigerator temperature should be 40 °F or below; the freezer, 0 °F or lower. If you're not sure a particular food is cold enough, take its temperature with a food thermometer.

### Frequently Asked Questions:

**Q** Flood waters covered our food stored on shelves and in cabinets. What can I keep and what should I throw out?

**A** Do not eat any food that may have come into contact with flood water.

- Discard any food that is not in a waterproof container if there is any chance that it has come into contact with flood water. Food containers that are not waterproof include those with screw-caps, snap lids, pull tops, and crimped caps. Also, discard cardboard juice/milk/baby formula boxes and home canned foods if they have come in contact with flood water, because they cannot be effectively cleaned and sanitized.

The Food Safety and Inspection Service (FSIS) is the public health agency in the U.S. Department of Agriculture responsible for ensuring that the nation's commercial supply of meat, poultry, and egg products is safe, wholesome, and correctly labeled and packaged.

**USDA Meat & Poultry Hotline**  
**1-888-MPHotline**  
(888-674-6854)

- Inspect canned foods and discard any food in damaged cans. Can damage is shown by swelling, leakage, punctures, holes, fractures, extensive deep rusting, or crushing/denting severe enough to prevent normal stacking or opening with a manual, wheel-type can opener.

### Steps to Salvage All-Metal Cans and Retort Pouches

Undamaged, commercially prepared foods in all-metal cans and retort pouches (for example, flexible, shelf-stable juice or seafood pouches) can be saved if you do the following:

- Remove the labels, if they are the removable kind, since they can harbor dirt and bacteria.
- Thoroughly wash the cans or retort pouches with soap and water, using hot water if it is available.
- Brush or wipe away any dirt or silt.
- Rinse the cans or retort pouches with water that is safe for drinking, if available, since dirt or residual soap will reduce the effectiveness of chlorine sanitation.
- Then, sanitize them by immersion in one of the two following ways:
  - Place in water and allow the water to come to a boil and continue boiling for 2 minutes, or
  - Place in a freshly made solution consisting of 1 tablespoon of unscented, liquid chlorine bleach per gallon of drinking water (or the cleanest, clearest water available) for 15 minutes.
- Air-dry cans or retort pouches for a minimum of 1 hour before opening or storing.
- If the labels were removable, then re-label your cans or retort pouches, including the expiration date (if available), with a marker.
- Food in reconditioned cans or retort pouches should be used as soon as possible, thereafter.
- Any concentrated baby formula in reconditioned, all-metal containers must be diluted with clean, drinking water.

### Q How should I clean my pots, pans, dishes, and utensils?

**A** Thoroughly wash metal pans, ceramic dishes, and utensils (including can openers) with soap and water, using hot water if available. Rinse and then sanitize them by boiling in clean water or immersing them for 15 minutes in a solution of 1 tablespoon of unscented, liquid chlorine bleach per gallon of drinking water (or the cleanest, clearest water available).

### Q How should I clean my countertops?

**A** Thoroughly wash countertops with soap and water, using hot water if available. Rinse and then sanitize them by applying a solution of 1 tablespoon of unscented, liquid chlorine bleach per gallon of drinking water (or the cleanest, clearest water available). Allow to air-dry.

### Q My home was flooded and I am worried about the safety of the drinking water. What should I do?

**A** Use **bottled water** that has not been exposed to flood waters if it is available.

- If you don't have bottled water, you should **boil water** to make it safe. Boiling water will kill most types of disease-causing organisms that may be present. If the water is cloudy, filter it through clean cloths or allow it to settle, and draw off the clear water for boiling. Boil the water for **one minute**, let it cool, and store it in clean containers with covers.

- If you can't boil water, you can **disinfect it using household bleach**. Bleach will kill some, but not all, types of disease-causing organisms that may be in the water. If the water is cloudy, filter it through clean cloths or allow it to settle, and draw off the clear water for disinfection. Add **1/8 teaspoon (or 8 drops)** of regular, unscented, liquid household bleach **for each gallon of water**, stir it well and let it stand for 30 minutes before you use it. Store disinfected water in clean containers with covers.

- If you have a well that has been flooded, the water should be tested and disinfected after flood waters recede. If you suspect that your well may be contaminated, contact your local or state health department or agriculture extension agent for specific advice.

**Q** We had a fire in our home and I am worried about what food I can keep and what to throw away.

**A** Discard food that has been near a fire. Food exposed to fire can be damaged by the heat of the fire, smoke fumes, and chemicals used to fight the fire. Food in cans or jars may appear to be okay, but the heat from a fire can activate food spoilage bacteria. If the heat is extreme, the cans or jars themselves can split or rupture, rendering the food unsafe.

One of the most dangerous elements of a fire is sometimes not the fire itself, but toxic fumes released from burning materials. Discard any raw food or food in permeable packaging-cardboard, plastic wrap, screw-topped jars, bottles, etc.-stored outside the refrigerator. Food stored in refrigerators or freezers can also become contaminated by fumes. The refrigerator seal isn't airtight and fumes can get inside. Chemicals used to fight the fire contain toxic materials and can contaminate food and cookware. Food that is exposed to chemicals should be thrown away-the chemicals cannot be washed off the food. This includes food stored at room temperature, such as fruits and vegetables, as well as food stored in permeable containers like cardboard and screw-topped jars and bottles. Cookware exposed to fire-fighting chemicals can be decontaminated by washing in soap and hot water. Then submerge for 15 minutes in a solution of 1 tablespoon unscented, liquid chlorine bleach per gallon of water.

**Q** A snowstorm knocked down the power lines, can I put the food from the refrigerator and freezer out in the snow?

**A** No, frozen food can thaw if it is exposed to the sun's rays even when the temperature is very cold. Refrigerated food may become too warm and foodborne bacteria could grow. The outside temperature could vary hour by hour and the temperature outside will not protect refrigerated and frozen food. Additionally, perishable items could be exposed to unsanitary conditions or to animals. Animals may harbor bacteria or disease; never consume food that has come in contact with an animal. Rather than putting the food outside, consider taking advantage of the cold temperatures by making ice. Fill buckets, empty milk cartons or cans with water and leave them outside to freeze. Then put the homemade ice in your refrigerator, freezer, or coolers.

**Q** Some of my food in the freezer started to thaw or had thawed when the power came back on. Is the food safe? How long will the food in the refrigerator be safe with the power off?

**A** **Never taste food to determine its safety!** You will have to evaluate each item separately. If an appliance thermometer was kept in the freezer, read the temperature when the power comes back on. If the appliance thermometer stored in the freezer reads 40 °F or below, the food is safe and may be refrozen. If a thermometer has not been kept in the freezer, check each package of food to determine the safety. Remember you can't rely on appearance or odor. If the food still contains ice crystals or is 40 °F or below, it is safe to refreeze. Refrigerated food should be safe as long as power is out no more than 4 hours. Keep the door closed as much as possible. Discard any perishable food (such as meat, poultry, fish, eggs, and leftovers) that have been above 40 °F for 2 hours.

**Q** May I refreeze the food in the freezer if it thawed or partially thawed?

**A** Yes, the food may be safely refrozen if the food still contains ice crystals or is at 40 °F or below. You will have to evaluate each item separately. Be sure to discard any items in either the freezer or the refrigerator that have come into contact with raw meat juices. Partial thawing and refreezing may reduce the quality of some food, but the food will remain safe to eat. See the attached charts for specific recommendations.

## REFRIGERATOR FOODS

*When to Save and When to Throw It Out*

FOOD	Held above 40 °F for over 2 hours
<b>MEAT, POULTRY, SEAFOOD</b>	
Raw or leftover cooked meat, poultry, fish, or seafood; soy meat substitutes	Discard
Thawing meat or poultry	Discard
Meat, tuna, shrimp, chicken, or egg salad	Discard
Gravy, stuffing, broth	Discard
Lunchmeats, hot dogs, bacon, sausage, dried beef	Discard
Pizza – with any topping	Discard
Canned hams labeled “Keep Refrigerated”	Discard
Canned meats and fish, opened	Discard
<b>CHEESE</b>	
Soft Cheeses: blue/bleu, Roquefort, Brie, Camembert, cottage, cream, Edam, Monterey Jack, ricotta, mozzarella, Muenster, Neufchatel, queso blanco, queso fresco	Discard
Hard Cheeses: Cheddar, Colby, Swiss, Parmesan, provolone, Romano	Safe
Processed Cheeses	Safe
Shredded Cheeses	Discard
Low-fat Cheeses	Discard
Grated Parmesan, Romano, or combination (in can or jar)	Safe
<b>DAIRY</b>	
Milk, cream, sour cream, buttermilk, evaporated milk, yogurt, eggnog, soy milk	Discard
Butter, margarine	Safe
Baby formula, opened	Discard
<b>EGGS</b>	
Fresh eggs, hard-cooked in shell, egg dishes, egg products	Discard
Custards and puddings	Discard
<b>CASSEROLES, SOUPS, STEWS</b>	Discard
<b>FRUITS</b>	
Fresh fruits, cut	Discard
Fruit juices, opened	Safe
Canned fruits, opened	Safe
Fresh fruits, coconut, raisins, dried fruits, candied fruits, dates	Safe

FOOD	Held above 40 °F for over 2 hours
<b>SAUCES, SPREADS, JAMS</b> Opened mayonnaise, tartar sauce, horseradish	Discard if above 50 °F for over 8 hrs.
Peanut butter	Safe
Jelly, relish, taco sauce, mustard, catsup, olives, pickles	Safe
Worcestershire, soy, barbecue sauces, Hoisin sauce	Safe
Fish sauces (oyster sauce)	Discard
Opened vinegar-based dressings	Safe
Opened creamy-based dressings	Discard
Spaghetti sauce, opened jar	Discard
<b>BREAD, CAKES, COOKIES, PASTA, GRAINS</b> Bread, rolls, cakes, muffins, quick breads, tortillas	Safe
Refrigerator biscuits, rolls, cookie dough	Discard
Cooked pasta, rice, potatoes	Discard
Pasta salads with mayonnaise or vinaigrette	Discard
Fresh pasta	Discard
Cheesecake	Discard
Breakfast foods –waffles, pancakes, bagels	Safe
<b>PIES, PASTRY</b> Pastries, cream filled	Discard
Pies – custard, cheese filled, or chiffon; quiche	Discard
Pies, fruit	Safe
<b>VEGETABLES</b> Fresh mushrooms, herbs, spices	Safe
Greens, pre-cut, pre-washed, packaged	Discard
Vegetables, raw	Safe
Vegetables, cooked; tofu	Discard
Vegetable juice, opened	Discard
Baked potatoes	Discard
Commercial garlic in oil	Discard
Potato Salad	Discard

## FROZEN FOOD

*When to Save and When to Throw It Out*

FOOD	Still contains ice crystals and feels as cold as if refrigerated	Thawed. Held above 40 °F for over 2 hours
<b>MEAT, POULTRY, SEAFOOD</b>		
Beef, veal, lamb, pork, and ground meat	Refreeze	Discard
Poultry and ground poultry	Refreeze	Discard
Variety meats (liver, kidney, heart, chitterlings)	Refreeze	Discard
Casseroles, stews, soups	Refreeze	Discard
Fish, shellfish, breaded seafood products	Refreeze. However, there will be some texture and flavor loss.	Discard
<b>DAIRY</b>		
Milk	Refreeze. May lose some texture.	Discard
Eggs (out of shell) and egg products	Refreeze	Discard
Ice cream, frozen yogurt	Discard	Discard
Cheese (soft and semi-soft)	Refreeze. May lose some texture.	Discard
Hard cheeses	Refreeze	Refreeze
Shredded cheeses	Refreeze	Discard
Casseroles containing milk, cream, eggs, soft cheeses	Refreeze	Discard
Cheesecake	Refreeze	Discard
<b>FRUITS</b>		
Juices	Refreeze	Refreeze. Discard if mold, yeasty smell, or sliminess develops.
Home or commercially packaged	Refreeze. Will change texture and flavor.	Refreeze. Discard if mold, yeasty smell, or sliminess develops.
<b>VEGETABLES</b>		
Juices	Refreeze	Discard after held above 40 °F for 6 hours.
Home or commercially packaged or blanched	Refreeze. May suffer texture and flavor loss.	Discard after held above 40 °F for 6 hours.

## FROZEN FOOD

*When to Save and When to Throw It Out*

FOOD	Still contains ice crystals and feels as cold as if refrigerated	Thawed. Held above 40 °F for over 2 hours
<b>BREADS, PASTRIES</b>		
Breads, rolls, muffins, cakes (without custard fillings)	Refreeze	Refreeze
Cakes, pies, pastries with custard or cheese filling	Refreeze	Discard
Pie crusts, commercial and homemade bread dough	Refreeze. Some quality loss can occur.	Refreeze. Quality loss is considerable.
<b>OTHER</b>		
Casseroles – pasta, rice based	Refreeze	Discard
Flour, cornmeal, nuts	Refreeze	Refreeze
Breakfast items –waffles, pancakes, bagels	Refreeze	Refreeze
Frozen meal, entree, specialty items (pizza, sausage and biscuit, meat pie, convenience foods)	Refreeze	Discard

## Food Safety Questions?

### Call the USDA Meat & Poultry Hotline

If you have a question about meat, poultry or egg products, call the USDA Meat and Poultry Hotline toll free at **1-888-MPHotline** or **1-888-674-6854**, TTY: 1-800-256-7072.



The hotline is open year-round Monday through Friday

from 10 a.m. to 4 p.m. EST (English or Spanish).

Listen to timely recorded food safety messages at the same number 24 hours a day. Check out the FSIS Web site at [www.fsis.usda.gov](http://www.fsis.usda.gov).

Send e-mail questions to [MPHotline.fsis@usda.gov](mailto:MPHotline.fsis@usda.gov).

### Ask Karen!

FSIS' automated response system can provide food safety information 24/7



[www.fsis.usda.gov](http://www.fsis.usda.gov)